

Sentinel RMS License Manager Guide on Commuter Licensing

Elysium Co. Ltd.

Last Updated: June 16, 2017


IMPORTANT NOTICE

It is reported that the number of remaining licenses was invalid when using Commuter Licensing function with Sentinel RMS License Manager v9.1.0.0104. Therefore, please ensure to use v9.1.0.1502 or later in case you plan to use Commuter Licensing function.

You can check the version with "WlmAdmin.exe". Please refer to "Sentinel RMS License Manager Setup & Quick Start Guide: 1-4)" for the instruction. After going step 1. and step 2. of 1-4), please check the "Version" displayed at upper right of the window.


1. Bringing out the License (Commuter Licensing)

This is the function to bring the licenses out of the network temporarily. The license server and the client computer should be network-connected to bring out the license registered to Sentinel RMS License Manager.



2. Prerequisite


- Please confirm that the commuter licensing function is activated (the value for "Commuter license" is "Yes") from "Detailed information" of each license on "WlmAdmin." It is not available to bring out the license when the value for "Commuter license" is "No."






- Please note that the license port should be set for 5093 to use the commuter license function.
- The version of applications such as Sentinel RMS License Manager and WCommute.exe should match. (You can check the version information from [Property] > [Details] of the context menu of executable file for each application.)

3. How to Bring out and back a License


1. Download "license_admin2" folder and copy to any folder regardless of shared or local directory in the client machine to install a tool to bring out the licenses on to the client machine.
2. Confirm that the server machine and a client machine are network-connected.
3. Run Isinit.exe in the license_admin2 folder. Specify the server where to bring out the license from for "Server Name," and 5093 for "Port Number." And then click [OK]. A message "Succeeded to initialize" will appear once it is completed successfully.



4. Run WCommute.exe. Please note that it requires administrative privileges to run this program.
5. Click [Search Subnet] button when both the server computer and the client computer(s) are installed within the same subnet, or click [Single Server] and specify either computer name or IP address of server computer when the server computer and the client computer(s) are installed to different subnets, to get a list of the licenses under each license server.
6. Click a license you want to bring out to specify the time to bring out the licenses. (unit=day)
The maximum length is 30 days. Please remember to bring out all the needed licenses which are most likely more than two.
7. Click [Check Out] button to bring out the licenses. The red check on the icon indicates that the license is currently brought out. ( -> )
8. Select "Commuter" in the dialog when starting Elysium application on a client computer, and then click [OK].
You can also change to use a commuter license from [License Setting] (Reboot will be required).



9. Select the license and click [Check In] button to bring back the license. Please note that the license will be automatically brought back after the specified period.



4. FAQ

Q1: Can I specify the period longer than 30 days when I bring out licenses?

A1: No. To avoid the risks to lose the license or so on, the period to bring out the license is limited up to 30 days.

Q2: How can I solve an error in bringing back the license?

A2: Please make sure to operate via exactly the same network; the same LAN port via wired LAN, or the same access point via wireless LAN.

Q3: Is it possible to return the license for any reason by an unofficial way?

A3: No. You just need to wait till the license will be returned due to the expiration of the specified period. To avoid any risks, it will be important to specify the minimum period.

Q4: When running "WRCommuter.exe" on computer with some of non-English version of Windows 8, 8.1, or 10, [Install] button on "Install Remote Authorization Code" tab is not displayed correctly and cannot be clicked.

A4: Please run "rcommute.exe" from the command-line interface.